




# Syniti Replicate

Setup Guide for MongoDB Atlas Targets

Version 10.1



## Table of Contents

- Introduction.....1
  - Basic Configuration Steps .....1
- Connection Type .....1
- Setup Summary .....2
- Download and Install Syniti Replicate .....2
- Download and Install .NET Provider.....2
- Steps for Replicating Tables .....3
  - 1. Set Up a Source Connection to a Relational Database.....4
  - 2. Configure the Enable Transactional Replication Wizard .....7
  - 3. Set up a Target Connection to MongoDB .....9
  - 3. Add Table Information to the Target Connection.....13
  - 4. Define Replications.....15
- Start Replications .....18
- Stop Replications .....19
- Replication Results.....19

# Syniti Replicate

## Introduction

Syniti Replicate allows you to replicate data from relational database tables to MongoDB Atlas, a cloud-based document database, using:

- **Refresh**, or **Snapshot**, replication: a one-time complete replication from any major relational database source to MongoDB as a target, according to replication settings and scripts.
- **Mirroring**, or **Change Data Capture**, replication: a continuous read of changes to the source database that have been recorded in the database server log. Any changes found in the log are applied to MongoDB as a target, according to replication settings and scripts.

MongoDB stores data in flexible consistently formatted documents. All records in MongoDB are associated with a specific *collection* inside a database. When replicating data using Syniti Replicate to MongoDB, the MongoDB file system is virtualized as relational tables (with columns and data types). You can create a target table and define a replication to a MongoDB target, applying mappings and expression logic as you would normally do with relational database targets. The MongoDB message is built internally using a JSON serialization of the entire record. Every replication must be associated with a MongoDB collection, so that Syniti Replicate can determine where to publish the message.

You can control the timing of the replication, identify the columns to be replicated and add scripts to transform data during replication. Source databases include Oracle, Microsoft SQL Server, IBM Db2 for i, IBM Db2 LUW, Sybase, Informix, MySQL.

## Basic Configuration Steps

Use Syniti Replicate Management Center to:

- Create source connections to RDBMS tables
- Create MongoDB targets
- Map RDBMS sources to MongoDB targets
- Enable replication

## Connection Type

For MongoDB 4.0, use .NET Driver Version 2.8.0. The latest stable version can be downloaded via:

<https://www.nuget.org/packages/MongoDB.Driver/2.8.0>

See [Download and Install .NET Provider](#) for more detail on installing the provider.

# Syniti Replicate

## Setup Summary

This section provides a summary of all the steps required for setting up and using Syniti Replicate. Use the link for each step for more information.

<b>Download and Install Syniti Replicate</b>	<p>The <a href="#">Knowledge Platform Product Suites article</a> acts as a hub to point to various resources. To download and/or register Syniti Replicate, log in to the support site, then click the relevant link in the Replicate section of the article.</p> <ul style="list-style-type: none"><li>• <a href="#">Syniti Knowledge Base</a></li><li>• <a href="#">Enter a generic support ticket</a></li></ul>
<b>Install .NET Provider for Source Database</b> (See <a href="#">Download and Install .NET Provider</a> )	<ol style="list-style-type: none"><li>3. Go to <a href="https://www.nuget.org/packages/MongoDB.Driver/2.8.0">https://www.nuget.org/packages/MongoDB.Driver/2.8.0</a></li><li>4. Run the nuget.exe command line tool.</li><li>5. Extract the correct version of the provider files.</li></ol>
<b>Syniti Replicate Setup</b>	<p>In the Syniti Replicate Management Center:</p> <ol style="list-style-type: none"><li>1. In the Metadata Explorer, create a source connection to your RDBMS.</li><li>2. Create a target connection using the MongoDB Atlas option in the <b>Database</b> field.</li><li>3. Create a replication.</li></ol>
<b>Start Replicating</b>	<p>In the Syniti Replicate Service Monitor:</p> <ol style="list-style-type: none"><li>1. Start the Replication Agent.</li></ol>

## Download and Install Syniti Replicate

To download and/or register Syniti Replicate, log in to the [support site](#), then click the relevant link in the Replicate section of the article.


## Download and Install .NET Provider

On the system where you plan to install Syniti Data Replication, make sure that you are running Microsoft .NET Framework 4.8 or above.

1. Install the .NET provider for MongoDB. The link for the download is the following:  
<https://www.nuget.org/packages/MongoDB.Driver/2.8.0>  
This link includes all the assemblies needed to run the provider.
2. Run the nuget.exe command line tool (downloadable from [www.nuget.org/downloads](http://www.nuget.org/downloads)):  
`nuget install MongoDB.Driver -Version 2.8.0 -Framework net480 -OutputDirectory E:\Utils\Nuget\MongoDB`  
This command downloads all assemblies into the specified folder. However, there are separate folders for each of the assemblies:


Copyright© 2022 by BackOffice Associates, LLC d/b/a Syniti and/or affiliates. All Rights Reserved. This document contains confidential and proprietary information and reproduction is prohibited unless authorized by Syniti. Names appearing within the product manuals may be trademarks of their respective owners.

# Syniti Replicate



Name	Date modified	Type	Size
DnsClient.1.2.0	5/16/2019 11:58 AM	File folder	
MongoDB.Bson.2.8.0	5/16/2019 11:58 AM	File folder	
MongoDB.Driver.2.8.0	5/16/2019 11:58 AM	File folder	
MongoDB.Driver.Core.2.8.0	5/16/2019 11:58 AM	File folder	
System Buffers.4.4.0	5/16/2019 11:58 AM	File folder	
System.Runtime.InteropServices.Runtime...	5/16/2019 11:58 AM	File folder	

3. Open each folder and extract the version of the .dll that is:
- Valid for .NET framework 4.8 or earlier (**netxx**), if available OR
  - Use the latest .NET Standard framework (**netstandardxx**) version
- For instance, the DnsClient.1.2.0 contains the following subfolders:



Name	Date modified	Type	Size
net45	5/16/2019 11:58 AM	File folder	
net471	5/16/2019 11:58 AM	File folder	
netstandard1.3	5/16/2019 11:58 AM	File folder	
netstandard2.0	5/16/2019 11:58 AM	File folder	

For .NET Framework 4.8 installations, you cannot use the net471 folder because it is higher than 4.6, but you can use net45. If that were not included, you would select netstandard2.0.

4. Copy the extracted assemblies to <SynitiDR-install-dir>/Plugins/MongoDB/:
- DnsClient.dll
  - MongoDB.BSon.dll
  - MongoDB.Driver.dll
  - MongoDB.Driver.Core.dll
  - System.Buffers.dll
  - System.Runtime.InteropServices.RuntimeInformation.dll

## Steps for Replicating Tables

Syniti Replicate support for replicating relational data to MongoDB Atlas allows you to set up replications using either **Refresh** or **Mirroring** modes.


The steps below explain how to replicate data from a relational database to MongoDB. Check [the Help Center](#) for the latest list of supported databases.



# Syniti Replicate

## 1. Set Up a Source Connection to a Relational Database


1. Make sure you have database connections via a .NET data provider to your source database. For each database you are planning to use in your replication project:
  - Install and configure your .NET Provider.
  - From the provider, test the connection to the database.
  - Create a connection string for the data access product/database you are using. Check the documentation for the data access product for information on how to do this.
  - Check that the user ID you are planning to use has sufficient permissions to complete all operations in Syniti Replicate. Use the [Help Center](#) to [download a Setup Guide](#) for your database for additional details.
2. Start Syniti Replicate Management Center.  
Syniti Replicate provides a default database (Microsoft SQL Server CE) for your metadata, all the information that Syniti Replicate needs to store about your replication setup.



3. In the Metadata Explorer, expand the metadata node to view the **Sources** and **Targets** nodes.
4. Select the **Sources** node.

# Syniti Replicate

- From the right mouse button menu, choose **Add New Connection**.



- In the Source Connection Wizard, follow steps to add a connection string and test the connection to the database.
- Check the Syniti Replicate User's Guide **Database Access Providers and Supported Databases** page to verify what value to enter in the **Assembly** field.

# Syniti Replicate

**Add Source Connection Wizard**

Syniti Replicate

Select the database that contains source data to be replicated and indicate which provider to use.

**Select provider**

Set connection string

Select tables

Actions

Summary

Source name

Name: IBMDB2i-Src

Data Provider(s)

Database: IBM Db2 for i

Provider: HiT Software .NET Driver (Ritmo/i)

Assembly: Ritmo\_i/lib/Sql400.dll

Browse

< Back Next > Cancel Help


8. In the **Set Connection String** screen, fill out the following fields:

### Connection Properties

Edit at least the **Required** connection properties by clicking in the property value field and typing a new value.

9. Click **Next** to choose the tables that you plan to replicate.
10. If using Refresh mode to replicate data to MongoDB, in the **Actions** screen, check the option **Launch the Add Target Connection Wizard**.  
-OR-  
If using Mirroring mode to replicate data to MongoDB, in the **Actions** screen, check the option **Launch the Enable Transactional Replication Wizard**.





## 2. Configure the Enable Transactional Replication Wizard


Skip this section if you are setting up a Refresh replication. Continue here if you are setting up a Mirroring replication.

This section assumes you have checked the Source Connection wizard option to launch the Enable Transactional Replication wizard. To open the wizard from the Management Center, choose the connection in the Metadata Explorer, then right-click to choose **Transactional Setup > Enable...**

In the **Enable Transactional Replication** wizard:

1. Select the type of transactional replication to use. The options depend on the source database and can include Log Reader, Log Server Agent, Triggers, plus Log Reader API (for IBM Db2 for i only.)

# Syniti Replicate



- Click **Next** to enter the log settings. The fields and appropriate values depend on the database and log type. Use the [Help Center](#) to [download a Setup Guide](#) for your database.
- All Log Server Agent setups require the following Agent Settings to establish details for the Windows service and log files:

### **Log Files Folder**

An existing folder where all the intermediate binary logs files are written. The folder is also used to contain trace files.

### **Prefix**

A prefix for all files created in the folder. This provides easy identification and management of files associated with your connection. The primary purpose for the prefix is to support the case when you configure more than one connection to use the same folder. In general, however, it is advisable to use different folders for different connections.

### **Log File Size**

Copyright© 2022 by BackOffice Associates, LLC d/b/a Syniti and/or affiliates. All Rights Reserved. This document contains confidential and proprietary information and reproduction is prohibited unless authorized by Syniti. Names appearing within the product manuals may be trademarks of their respective owners.

# Syniti Replicate

The maximum size of each binary log file in megabytes.

## **Keep Max Files**

The maximum number of binary log files to keep. Combined with the log file size, this number needs to be large enough to make sure that all the files are read by Syniti Replicate before they get deleted.

## **Trace**

Unchecked by default. When checked, enables tracing for diagnostics and problem reporting. Trace files are saved in the Log Server folder.

## **Windows Service Name**

### **Prefix:**

This value is provided and cannot be changed. It allows you to easily identify the service in the Microsoft Windows Services tool.

### **Name:**

Specify a unique name for the Windows service. Each connection runs its own instance of the Log Server as a Windows service.

### **Start service after completing the wizard:**

When checked, starts the service automatically after you click **Finish** to complete the wizard.


4. Click **Next** to verify your settings against the source connection to the database. If any information is missing, you will not be able to proceed.
5. In the **Actions** screen, check the option **Launch Add Target Connection Wizard**.
6. Click **Next** to review your changes.
7. Click **Finish** to complete the wizard.

The source connection is now set up for transactional replications.

## 3. Set up a Target Connection to MongoDB

1. Select the **Targets** node.
2. From the right mouse button menu, choose **Add New Connection**.

# Syniti Replicate



3. In the Add Target Connection Wizard **Database** field, select the MongoDB Atlas option. The **Provider** and **Assembly** fields are automatically filled out for you.

# Syniti Replicate

**Add Target Connection Wizard**

Syniti Replicate

Select the database target where to replicate data and indicate which provider to use.

**Select provider**

Set connection string

Set staging connection string

Select tables

Actions

Summary

**Target name**

Name: MongoDB

**Data Provider(s)**

Database: MongoDB Atlas

Provider: MongoDB Data Provider

Assembly: Plugins/MongoDB/DataAccess.Plugins.MongoDB.dll

Browse

< Back Next > Cancel Help

4. In the **Set Connection String** page, set properties as described in the table below. The table displays only properties specific for use with Syniti Replicate. You can also set additional MongoDB properties as needed.

# Syniti Replicate

<b>Server</b>	The server name or IP address of the MongoDB instance.
<b>Port</b>	The port number of the server MongoDB.
<b>Use DNS Seedlist</b>	If set to false, the standard connection format is used. If set to true, a DNS-constructed seed list is used. Using DNS to construct the available servers list allows more flexibility of deployment and the ability to change the servers in rotation without reconfiguring clients.
<b>User ID</b>	User name for MongoDB Atlas
<b>Password</b>	Password for MongoDB Atlas
<b>Database</b>	MongoDB database name
<b>Output Folder</b>	The schema name and location to hold config files for the MongoDB objects.
<b>Default Collection</b>	All MongoDB replications need to be targeted to a specific collection. Use this field to indicate a default collection for all replications in that connection. Alternatively, if the Default Collection is left blank, every replication will need a collection name.
<b>Create Collection Per Table</b>	If set to true, every new replication will attempt to use the collection named as the target table. If the collection does not exist, it will be created using the Syniti Replicate table name.



# Syniti Replicate

Use One Writer Per Group	Default is True. When True, Syniti Replicate uses a single writer object common to all replications in a group (if groups are used). When False, a new object is created for each replication.
--------------------------	--

5. Click **Next** to display the **Select tables** page.  
At this point, there is no text output structure available to display. You can add the information after completing the Target Connection wizard.
6. Click **Next** to display the **Summary** page.
7. Click **Finish** to complete the wizard.

## 3. Add Table Information to the Target Connection

The target connection is displayed in the Metadata Explorer, but you still need to add the file representation for source table data so that when you create replications below, you can specify a source table and target “file.”

1. In the Metadata Explorer, expand the source connection you created above.
2. Select and drag a source table to the target file connection.  
The Create Target Table wizard is displayed. Although you are not actually creating tables, you can use this wizard to create a representation of the data.
3. In the **Source Connection** screen, you should see the source table you selected above.
4. Click **Next** to display the **Target Connection** screen.
5. Verify that the screen displays the correct target connection name, and table name.
6. Click **Next** to review the table structure.  
At this point, you can modify data types, null values and so on, if you want to modify the data eventually sent to a file.
7. Click **Next** to display the **SQL Script** screen.  
The contents of this screen are inactive because there is no editable SQL script to create a table. Instead, Syniti Replicate outputs the table information to a file.
8. Click **Next** to display the **Summary** screen.
9. Click **Finish** to create the table representation in the Metadata Explorer.
10. Click **Yes** to add the table name to the target connection entry in the Metadata Explorer
11. Repeat steps 2 through 11 for each source table that you want to replicate to a file.

At the end of this process, you should have a list of table representations under the target connection in the Metadata Explorer.

If you select the table and edit the Properties, there is a new property called **Collection Name**:

# Syniti Replicate

General	
Connection Name	MongoDB
Table Name	employees
Type	mongoDB
System Name	
Object Id	
Description	
Collection Name	employees

Performance Metrics	
Record Size	22
Contains LOB Fields	False

**Connection Name**  
Connection used for the table.

OK Cancel

**Collection Name** can be edited. If blank, Syniti Replicate uses the **Default Collection** property of the connection to determine to which collection to deliver the records. Otherwise, it uses the collection indicated in this field.

Note that if you replicate a table that has a blank collection value both here and, in the connection, the Replication Agent generates an error and disables the replication, unless you set the **Create Collection Per Table** property to True, in which case a collection will be created automatically.

# Syniti Replicate

## 4. Define Replications

1. Expand the Metadata Explorer tree to display the table that contains the data you want to replicate.
2. Select the table.
3. From the right mouse button menu, choose **Replication** then **Create New Replication....**
4. In the Define Replication Type screen, type a name to identify the replication.
5. Optionally provide a description of the replication.
6. In the **Replication Mode** area, choose **Refresh** or **Continuous Mirroring**.

**Create Replication Wizard**

Syniti Replicate

*Replication type*

Source connection

Source log info

Target connection

Target log info

Mapping info

Scheduling

Actions

Summary

Mirroring mode will define a one-way transactional replication, from the source server to the target server.

Replication Name

Replication Name: CUSTOMER

Description:

☐ Use Group: <undefined> Create

Replication Type

☐ Refresh

☒ Continuous Mirroring

☐ Synchronization

< Back Next > Cancel Help

7. Click **Next** to go to the **Select Source Connection** screen.

# Syniti Replicate

Create Replication Wizard

Syniti Replicate

Select the source connection and table to be replicated.

Replication type

**Source connection**

Source log info

Target connection

Target log info

Mapping info

Scheduling

Actions

Summary

Connection Name: IBMDB2i-Src

Table Name: OLETEST.CUSTOMER

Open Table...

< Back Next > Cancel Help

8. Choose the source connection name from the drop-down list that includes all the source connections you have created in Syniti Replicate.
9. Choose the table that you want to replicate from the drop-down list.
10. If you want more information about the table before proceeding, click **Open Table...**
11. Click **Next** to go to the **Source Log Info** screen.  
Complete the fields in this screen only if you are setting up a mirroring replication. The fields displayed depend on the source database log type.

# Syniti Replicate

Create Replication Wizard

## Syniti Replicate

Click Next to use the current transaction read point from the IBM i/AS400 server. To override, click Read TID to set the transaction ID from which to replicate.

Replication type

Source connection

**Source log info**

Target connection

Target log info

Mapping info

Scheduling

Actions

Summary

Journal:

Receiver:

Transaction ID:

Transaction Timestamp:

Read Interval (sec):

< Back   Next >   Cancel   Help

12. Click **Next** to go to the **Select Target Connection** screen.
13. Choose the target connection for text output from the drop-down list that includes all the target connections you have created in Syniti Replicate.
14. Choose the data set you want to replicate from the drop-down list.  
If the drop-down list is empty, exit the wizard and add or create a target data set.
15. Click **Next** to go to the **Set Mapping Info** screen.  
Source columns and target data with the same name are automatically mapped.
16. Click **Next** to go to the **Scheduling** screen.

# Syniti Replicate

Create Replication Wizard

Syniti Replicate

Replication type

Source connection

Source log info

Target connection

Target log info

Mapping info

**Scheduling**

Actions

Summary

Set scheduling information for the replication.

☒ Enable Replication

☒ Execute Initial Refresh

Start Time: 6/29/2022 2:10:45 PM

Refresh Schedule Mirroring Schedule Verifier Schedule

☒ Run One Time Only


☐ Run Recurrently:

Add Remove Edit

< Back Next > Cancel Help

17. Make sure the **Enable Replication** option is checked. This is required for the replication to run.
18. Set a start time for the replication. The **Start Time** field indicates the time at which the Replication Agent will begin considering the replication for execution.
19. Check the option to **Execute Initial Refresh**.  
A full replication will be performed from the source table to the data file.
20. Click **Next** to go to the **Summary** screen.
21. Click **Finish** to complete the wizard.

## Start Replications

If you installed the Replication Agent as a service during Syniti Replicate setup, you just need to start the service using the ServiceMonitor program  in the Windows Notification Area.



- The replication that you have scheduled should start at the specified time.
- Use the Replication Monitor tab in the Management Center to track the progress of the replication.

If you would like to set up the Replication Agent as a service:


Copyright© 2022 by BackOffice Associates, LLC d/b/a Syniti and/or affiliates. All Rights Reserved. This document contains confidential and proprietary information and reproduction is prohibited unless authorized by Syniti. Names appearing within the product manuals may be trademarks of their respective owners.



# Syniti Replicate

- From the Service Monitor program  in the Windows Notification Area, choose **Launch Service Installer**.
- Manage the service from Service Monitor program (located in the Windows Notification Area .
- Use the Replication Monitor tab in the Management Center to track the progress of the replication.

To run the Replication Agent interactively:

- In the Windows Notification Area, select the Service Monitor icon .
- From the right mouse button menu, choose **Replication Agent**, then **Start** then **Application**.  
The replication that you have scheduled should start at the specified time.
- Use the Replication Monitor tab in the Management Center to track the progress of the replication.

## Stop Replications

Stop the Replication Agent from the Service Monitor in the Windows Notification Area.

## Replication Results

Because MongoDB is not a standard relational database and only handles messages, it is not possible to open the content of a target table in the Management Center to verify if the replication has been successful. To do that, use another application that is able to act as a consumer to receive the messages sent to MongoDB.