Syniti

Data Replication

Setup Notes for Replicating with Snowflake®

Version 9.8.2





Syniti Data Replication

Table of Contents

Connection Type	3
Add a Target Connection Wizard	
Select Provider Screen	
Set Connection String Screen	

Syniti Data Replication

These notes provide essential information for setting up replications using Snowflake cloud data platform as:

- A target for Mirroring (change data capture)
- A source or target for Refresh replications

For complete details on the setup process, check the *User Guide* available from the Management Center **Help** menu.

Connection Type

Snowflake ODBC driver version 2.20 or above, available for download via a Snowflake documentation link: https://docs.snowflake.net/manuals/user-guide/odbc-download.html


NOTE: This driver requires the Microsoft Visual C++ Redistributable for Visual Studio 2015.

Add a Source/Target Connection Wizard

NOTE: If using Snowflake as a source in Refresh replications, perform the following steps in the **Add Source Connection wizard**.

For Refresh or Mirroring replications to a Snowflake target, configure a target connection in the Management Center using the information below. More information on the steps to configure a connection can be found in the User Guide (available from the Management Center.

Select Provider Screen



Select Snowflake in the Database field.

The **Provider** field automatically shows Snowflake ODBC Driver.

Copyright© 2022 by BackOffice Associates, LLC d/b/a Syniti and/or affiliates. All Rights Reserved. This document contains confidential and proprietary information and reproduction is prohibited unless authorized by Syniti. Names appearing within the product manuals may be trademarks of their respective owners.


Syniti Data Replication

Set Connection String Screen

Type an ODBC connection string in the field next to **Connection String** using the format in the sample connection string below.

DRIVER={SnowflakeDSIIDriver};UID=myUser;PWD=myPassword;DATABASE=myDB;SERVER=myServer;

NOTE: Clicking ... in the Connection String field opens up a dialog from the Snowflake ODBC driver that allows you to specify connection parameters but there can be an issue with saving the parameters. It is highly recommended that you specify the connection string by typing/pasting it in.



Copyright© 2022 by BackOffice Associates, LLC d/b/a Syniti and/or affiliates. All Rights Reserved. This document contains confidential and proprietary information and reproduction is prohibited unless authorized by Syniti. Names appearing within the product manuals may be trademarks of their respective owners.